

DALIBuildings Release Notes

CONTENTS

Contents	1
DALIBuildings 2.1.1 Release Notes.....	2
What's New	2
DCDALRM2 Support	2
Emergency Light & ECG Status Report Improvement	2
Other Issues.....	2

DALIBuildings 2.1.1 Release Notes

August 2016

WHAT'S NEW

DCDALRM2 SUPPORT

Changes made:

- The Clipsal 2 Channel Relay (DCDALRM2) can now be used during offline programming.
- The Extended properties of DCDALRM2 can now be configured.

EMERGENCY LIGHT & ECG STATUS REPORT IMPROVEMENT

Improvements made:

- Added page numbers to the PDF Report.
- Updated the Report Configuration so that the odd/even addresses now filter as expected.
- The Recapture Result (as a new Report) now supports more than 10 controllers.
- Updated the Recapture Result (override) so that the duration test report no longer shows the result for a function test.
- Fixed some display issues with respect to Building Level.

OTHER ISSUES

This release also addresses the following:

- Replace ECG functionality should now be working as expected.
- The Ballast Editor is now able to send a command to a specific group as expected.
- After loading an ECD Switch template, the ECD Switch's slave type is now synced correctly.
- After copying device type(s) from one controller to another, the newly copied device type(s) can now be exported to the legacy database format (mdb file).
- Device type 6, 7, 8 can now be exported to the legacy database format (mdb file).
- The ballast editor is now able to write to groups on Line B.
- When deleting a timer, it is now correctly deleted from the controller.
- Performing Sync All to multiple controllers is now able to sync the related devices as expected.